

UbuntuLinux操作系统CVS安装与配置详解 PDF转换可能丢失图片或格式，建议阅读原文

[https://www.100test.com/kao\\_ti2020/466/2021\\_2022\\_UbuntuLinu\\_c67\\_466644.htm](https://www.100test.com/kao_ti2020/466/2021_2022_UbuntuLinu_c67_466644.htm)

1. 安装 cvs \$ sudo apt-get install cvs  
2. 安装 cvsd \$ sudo apt-get install cvsd  
cvsd安装以后, 会提示设置“repository”的位置location, type in "/cvsroot". “RootJail” is setted in

“/etc/cvsd/cvsd.conf”, the default value is /var/lib/cvsd. This means, your repository location could be just “/cvsroot”  
3. 创建 /myrepos \$ cd /var/lib/cvsd \$ sudo mkdir cvsroot

4. 初始化 /cvsroot \$ sudo cvs -d /var/lib/cvsd/cvsroot init  
5. 设置cvsd用户鉴定 (user authentication) normal it ‘s system level, and the cvs users should be configured independently.

\$ sudo vi /var/lib/cvsd/cvsroot/CVSROOT/config 添加下面行:

SystemAuth=no PamAuth=no LockDir=/tmp/cvsroot Look out!

“/tmp/cvsroot” 和RootJail的位置是相关的.  
6. 创建 LockDir \$ sudo mkdir /var/lib/cvsd/tmp/cvsroot

7. 创建 users \$ sudo cvsd-passwd /var/lib/cvsd/cvsroot cvs-user  
8. 编辑 cvsd configuration \$ sudo vi /etc/cvsd/cvsd.conf  
The default one should be : RootJail /var/lib/cvsd Repos /cvsroot  
NOTICE! Repos路径也是和RootJail相关的.  
100Test 下载频道开通，各类考试题目直接下载。详细请访问 [www.100test.com](http://www.100test.com)